

KeyCode (value)

esc 27	f1 112	f2 113	f3 114	f4 115	f5 116	f6 117	f7 118	f8 119	f9 120	f10 121	f11 122	f12 123	prt scr	scr 145	pause 19					
~ 192	1 49	2 50	3 51	4 52	5 53	6 54	7 55	8 56	9 57	0 48	- 189	= 187	back 8	ins 45	home 36	page up 33	num 144	/ 111	* 106	-
tab 9	q 81	w 87	e 69	r 82	t 84	y 89	u 85	i 73	o 79	p 80	[219	] 221	\ 220	del 46	end 35	page down 34	7 103/36	8 104/38	9 105/33	+ 107
caps 20	a 65	s 83	d 68	f 70	g 71	h 72	j 74	k 75	l 76	; 186	' 222	enter 13					4 100/37	5 101/12	6 102/39	
shift 16		z 90	x 88	c 67	v 86	b 66	n 78	m 77	, 188	. 190	/ 191	shift 16			↑ 38		1 97/35	2 98/40	3 99/34	
ctrl 17	win 91	alt 18	space 32					alt 18	win 92	select 93	ctrl 17		← 37	↓ 40	→ 39		0 96/45	. 110/46	enter 13	

Keyboard Output (string)

esc <ESCAPE>	f1 <F1>	f2 <F2>	f3 <F3>	f4 <F4>					f5 <F5>	f6 <F6>	f7 <F7>	f8 <F8>					f9 <F9>	f10 <F10>	f11 <F11>	f12 <F12>				prt scr <PRINT>	scr <SCROLL>	pause <PAUSE>					
~ <KEY192>	1	2	3	4	5	6	7	8	9	0	- <KEY189>	= <KEY187>	back <BACK>					ins <INSERT>	home <HOME>	page up <PRIOR>				num <NUMLOCK>	/ <DEVIDE>	* <MULTIPLY>	- <SUBTRACT>				
tab <TAB>	Q	W	E	R	T	Y	U	I	O	P	[<KEY219>	] <KEY221>	\ <KEY220>					del <DELETE>	end <END>	page down <NEXT>				7 <NUMPAD7> <HOME>	8 <NUMPAD8> <UP>	9 <NUMPAD9> <PRIOR>	+ <ADD>				
caps <CAPITAL>	A	S	D	F	G	H	J	K	L	; <KEY186>	' <KEY222>	enter <RETURN>																			
shift <SHIFT>		Z	X	C	V	B	N	M	, <KEY188>	. <KEY190>	/ <KEY191>	shift <SHIFT>																			
ctrl <CONTROL>	win <LWIN>	alt <ALT>		space <SPACE>						alt <ALT>		win <RWIN>	select <APPS>	ctrl <CONTROL>				← <LEFT>	↓ <DOWN>	→ <RIGHT>				0 <NUMPAD0> <INSERT>	. <DECIMAL> <DELETE>	enter <RETURN>					